



SOLO Trumpet III

Thank you for purchasing SOLO Trumpet III!

This **SOLO Trumpet III Kontakt Library** was recorded using two microphones (**A** – large diaphragm with a cardioid pattern and **B** – ribbon mic with a figure eight pattern). CMusicpro's engineers, by means of these unique pairings, have produced a carefully-crafted finished product combining the condenser's smooth, natural complexity with the ribbon's extreme sensitivity. The large-diaphragm condenser signals were then summed, and the combined resultant tonal qualities were found to smooth the occasional harsh highs often produced by brass instruments. The end result is a clean clear high end. Additionally, this process enabled a truly mono-capable signal to be produced. Complete balance adjustments between **A** and **B** components are possible. Meticulous production techniques, combined with multiple articulations create the impression of a realistic live performance.

Trumpet performed by: Oleg Ruvinov

Recording & Editing: Vladimir Kuznetsov

Programming, Design & Script: Vladimir Kuznetsov

© 2016 Cmusic Production, LLC / All Rights Reserved,
Cmusic Production®

Watermark Protected.

MUSIC production

Features

- Legato Velocity control
- 3-x round robin sustain non vibrato for each note (4 layers)
- 3-x round robin staccato (3 layers)
- 3-x round robin marcato short (2 layers)
- 2/4 and 4/4 tempo sync swells (120 bpm default, 2 layers)
- Rips chromatic short, medium and long (3 layers)
- Rips glissando short, medium and long (3 layers)
- Sliders sustain (3 layers) and short with stop (3 layers)
- Fast trills between notes in octave range.
- 1.16 GB on disc, 2 665 samples, 44.1 KHz / 24-bit

Installation Notes

1. Please go to the download links you received after purchase and download all of the files.
2. Make sure you put all downloaded files into a single folder.
3. Unpack the downloaded files to any folder. Please note that the sample files you downloaded are a multi-part archive, so you do not need to extract every file; you only need to extract the first file that contains 'part1' in its name.
To extract your files we recommend using Winrar for PC users, or UnrarX or Rar-Expander for the Mac.
4. You need to have the full retail version of Kontakt 5.0 or later to use this library. **The free Kontakt Player does NOT support this library.**
5. Open the Kontakt 5 browser (look on the left-hand side of the Kontakt user interface) and click the "Files" tab. Find the library folder, which you extracted earlier, and double-click on the **SOLO Trumpet 3.nki** file which should be in that folder. You can use the Quick-Build Database option to allow Kontakt to find and store the location for faster browsing and loading.

You cannot use the "Libraries" tab to "Add Library" for this product. That feature is only available for encoded & locked "Powered-By-Kontakt" libraries.

Watch a video to learn how to add to **Kontakt Quick-Load** menu:

<https://www.youtube.com/watch?v=4USeGpi9EnM>.

MUSIC production

LEGATO & SUSTAIN (Polyphonic)

Use **C0** keyswitch to play **Legato** (Velocity 0 – 63)

Use **C0** keyswitch to play **Sustain** (Velocity 64 – 127)

Press keyswitch **D1** (Velocity 101 – 127) to change Legato Speed value.

Dynamics

To control the dynamics between layers use the controller ModWheel **CC1**.
LoPass filter is connected to the controller Expression **CC11** to control the sound dynamics.

Attack

Attack depends on the velocity. There are three modes of attack:
If “Staccato” Articulation loads, Attack is working.

Hot Keys:

A#0 – Sliders + Sustain (Velocity 0 – 63)

LFO Vibrato

Use Sustain Pedal (CC64) to control sound between non vibrato and LFO vibrato.

LFO vibrato – CC64

Intensity LFO vibrato – CC18

Frequency LFO vibrato – CC19

ARTICULATIONS

Staccato

Use **C#0** keyswitch to play **Staccato**

Marcato

Use **D0** keyswitch to play **Marcato**:

Swells

Use **D#0** keyswitch to play **Swells**:

Short Swells – Velocity (0 – 63)

Long Swells – Velocity (64 – 127)

Rips A

Use E0 keyswitch to play **Rips A** (Chromatic):

Short Rips – Velocity (0 – 41)

Medium Rips – Velocity (42 – 83)

Long Rips – Velocity (84 – 127)

Rips B

Use F0 keyswitch to play **Rips B** (Glissando):

Short Rips – Velocity (0 – 41)

Medium Rips – Velocity (42 – 83)

Long Rips – Velocity (84 – 127)

Fast Trills

Play another Key without releasing the First Key in Legato mode.

Sliders & Stop

Use A#0 keyswitch to play **Sliders & Stop** (Velocity 64 – 127)

Gliss Up

Gliss Up A – Velocity (0 – 63)

Gliss Up B – Velocity (64 – 127)

Load/Unload articulation samples with the yellow-black buttons:



Dyn.Range regulates volume difference between legato layers (pp – ff):



Vel.Range regulates volume difference between articulation layers (pp – ff):



Humanize on-off (Use D1 Key). Turn on D1 key (Velocity 1 – 100) to change the value of humanization

MUSIC production

CMP SOLO Trumpet III

Balance between
A–B microphones:



EQ and Filters on-off



Humanize on-off
or press keyswitch **D1**

Convolution Reverb

Turn on Convolution Reverb,
select the preset, the balance
between DRY and WET signals
and PreDelay.



Ambience

Turn on Ambience and select the
preset.

