

# MUSIC production

CMP BRIGHT Trumpet



# BRIGHT Trumpet

User`s manual



Thank you for purchasing our BRIGHT Trumpet!

Welcome to the CMusic Production BRIGHT Trumpet Library. A bright screaming trumpet is often lacking for the performance of characteristic pieces. We have tried to fill this gap. So, play and enjoy!

Trumpet performed by: Gennadiy Shornikoff  
Recording & Editing: Vladimir Kuznetsov  
Programming, Design & Script: Vladimir Kuznetsov  
© 2020 Cmusic Production, LLC / All Rights Reserved,  
Cmusic Production®.

CMP BRIGHT Trumpet

Watermark Protected.

You cannot use the “Libraries” tab to “Add Library” for this product. That feature is only available for encoded & locked “Powered-By-Kontakt” libraries.

Watch a video to learn how to add to **Kontakt Quick-Load** menu:  
<https://www.youtube.com/watch?v=4USeGpi9EnM>.

## Features

- True Legato Velocity control
- Sustain non vibrato (4 layers)
- Attack Velocity Control
- LFO Vibrato
- Staccato
- Marcato
- Swells (6 variants length)
- Rips (2 variants)
- Virtual Falls, Sliders, Ends, Glide, Growl, Flutter, Diminuendo, Shaker
- Glissando
- Live trills between notes
- Humanize function
- 183 MB on disc, 646 samples, 44.1 KHz / 24-bit

## Installation Notes

1. Please go to the download links you received after purchase and download all of the files.
2. Make sure you put all downloaded files into a single folder.
3. Unpack the downloaded file “**CMP BRIGHT Trumpet.rar**” to any folder. Place **.nki** file next to the Samples folder.

To extract your files we recommend using Winrar for PC users, or UnrarX or Rar-Expander for the Mac.

4. You need to have the full retail version of Kontakt 5.5.2 or later to use this library. **The free Kontakt Player does NOT support this library!**
5. Open the Kontakt 5 browser (look on the left-hand side of the Kontakt user interface) and click the “Files” tab. Find the library folder, which you extracted earlier, and double-click on the **BRIGHT Trumpet.nki** file which should be in that folder. You can use the Quick-Build Database option to allow Kontakt to find and store the location for faster browsing and loading.


## LEGATO

Use **C0** keyswitch to play **Legato**.

Default play: Slow Legato (Velocity 1 – 40), Fast Legato (Velocity 41 – 127).

Attack Velocity Control: Soft (Velocity 1 – 63), Hard (Velocity 81 – 127).

To change the KEYSwitch click on the label “Cmusic Production” and do it.



## Dynamics

To control the dynamics between layers use the controller ModWheel **CC1**. You can see the layer change (p, mp, mf, ff).

LoPass filter is connected to the controller Expression **CC11** to control the sound dynamics.

## Hot Keys:

- A-1 – Fade Out Note velocity control (0.5 sec – 4.5 sec),
- B-1 – Breath,
- G0 – Growl (Velocity 1 – 63),
- G0 – Flutter (Velocity 64 – 127),
- A0 – Falls,
- A#0 – Sliders + Sustain (Control Velocity Value),
- B0 – Ends (Control Velocity Value),
- C1 – Glide Note (Control Velocity Value),
- C#1 – Shaker (use **CC2** to Shake Rate),
- D1 – Hold **D1** to change character Falls, Glide or Rips,
- D#1 – Round-Robin sustain notes.


## LFO Vibrato

Use Sustain Pedal (**CC64**) or **F#0** to control sound between non vibrato and LFO vibrato.

Fade In LFO vibrato – **CC17** (from 0 to 660 ms)

Intensity LFO vibrato – **CC18**

Frequency LFO vibrato – **CC19**



## ARTICULATIONS

### Staccato

Use **C#0** keyswitch to play **Staccato**.

### Marcato

Use **D0** keyswitch to play **Marcato**.

### Swells

Use **D#0** keyswitch to play **Swells**:

- 1/4 Swells – Velocity (1 – 41),
- 2/4 Swells – Velocity (42 – 83),
- 3/4 Swells – Velocity (84 – 127)

Use **E0** keyswitch to play **Swells**:

- 4/4 Swells – Velocity (1 – 41),
- 6/4 Swells – Velocity (42 – 83),
- 8/4 Swells – Velocity (84 – 127).

### Rips

Use **E0** keyswitch to play **Rips**:

- Short Rips – Velocity (1 – 63),
- Long Rips – Velocity (64 – 127).

### Glissando (Hot Key)

Use **G#0** keyswitch Velocity Control to play **Glissango**:

- Slow Gliss – Velocity (1 – 50),
- Medium Gliss – Velocity (51 – 100),
- Fast Gliss – Velocity (101 – 127).

### Fall (Hot Key)

Use **A0** keyswitch Velocity Control to play **Fall**:

- Long Fall – Velocity (1 – 50),
- Medium Fall – Velocity (51 – 100),
- Short Fall – Velocity (101 – 127).

# MUSIC production

CMP BRIGHT Trumpet

**Bright Trumpet**

MP Output: st. 1 # Voices: 0 Max: 32 Purge Memory: 113.69 MB

Midi Ch: [A] 1

Legato C0 ● Growl G0 ●  
 Staccato C#0 ● Gliss fast G#0 ●  
 Marcato D0 ● Fall sh A0 ●  
 Sw-s 1/4 D#0 ● Sliders A#0 ●  
 Sw-s 4/4 E0 ● Ends B0 ●  
 Rips sh F0 ● Glide C1 ●

**Bright Trumpet**

Vib. Fade in Vib. Frequency  
 Vib. Intensity Expression

Dyn. Range  
 Vel. Range  
 Humanize  
 Att. Control

MUSIC production

**Bright Trumpet**

MP Output: st. 1 # Voices: 0 Max: 32 Purge Memory: 110.64 MB

Midi Ch: [A] 1

Legato C0 ● Growl G0 ●  
 Staccato C#0 ● Gliss slow G#0 ●  
 Marcato D0 ●  
 Sw-s 1/4 D#0 ●  
 Sw-s 3/4 E0 ●  
 Sw-s 6/4 F0 ●

**Bright Trumpet**

**ABOUT** Change KEY: C0

Producer Vladimir Kuznetsov  
 Recording Vladimir Kuznetsov  
 Design Vladimir Kuznetsov  
 Script Vladimir Kuznetsov  
 Trumpet player Gennadiy Shornikoff

SN: XXXXXX Version 1.01

MUSIC production